

LA-UR-19-30468

Approved for public release; distribution is unlimited.

Title: Can supershear transition be seen in damage and aftershock pattern?
Part one: Theory

Author(s): Bruhat, Lucile; Jara, Jorge; Antoine, Solene; Okubo, Kurama; Thomas, Marion Y.; Rougier, Esteban; Rosakis, Ares J.; Sammis, Charles; Klinger, Yann; Jolivet, Romain; Bhat, Harsha S.

Intended for: Report

Issued: 2019-10-16


Disclaimer:

Los Alamos National Laboratory, an affirmative action/equal opportunity employer, is operated by Triad National Security, LLC for the National Nuclear Security Administration of U.S. Department of Energy under contract 89233218CNA000001. By approving this article, the publisher recognizes that the U.S. Government retains nonexclusive, royalty-free license to publish or reproduce the published form of this contribution, or to allow others to do so, for U.S. Government purposes. Los Alamos National Laboratory requests that the publisher identify this article as work performed under the auspices of the U.S. Department of Energy. Los Alamos National Laboratory strongly supports academic freedom and a researcher's right to publish; as an institution, however, the Laboratory does not endorse the viewpoint of a publication or guarantee its technical correctness.

Can supershear transition be seen in damage and aftershock pattern?

Part one: Theory

Lucile Bruhat, J. Jara, S. Antoine, K. Okubo, M.Y. Thomas,
E. Rougier, A. J. Rosakis, C. Sammis, Y. Klinger, R. Jolivet & H.S. Bhat



What are the conditions for transitioning supershear?

As shown by Michel Bouchon, supershear ruptures are **rare** events

What are the conditions for transitioning supershear?

As shown by Michel Bouchon, supershear ruptures are **rare** events

Although easy to reproduce in theoretical and numerical studies, as early as Burridge (1973) and Andrews (1976).

Following the classical Burridge-Andrews criterion, as first sight they need to be triggered by high background shear stress.

In practice....

What are the conditions for transitioning supershear?

As shown by Michel Bouchon, supershear ruptures are **rare** events

Although easy to reproduce in theoretical and numerical studies, as early as Burridge (1973) and Andrews (1976).

Following the classical Burridge-Andrews criterion, as first sight they need to be triggered by high background shear stress.

In practice....

Associated with linear, narrow fault segments by field studies [Bouchon, et al., 2010]

➤ Homogenous stress-strength conditions ?

What are the conditions for transitioning supershear?

BUT Supershear rupture can develop when the rupture propagates from a region of high strength to a region of low strength [Dunham, 2007, Liu and Lapusta, 2008]

➤ Heterogeneous stress-strength conditions ?

What are the conditions for transitioning supershear?


BUT Supershear rupture can develop when the rupture propagates from a region of high strength to a region of low strength [Dunham, 2007, Liu and Lapusta, 2008]

➤ Heterogeneous stress-strength conditions ?


Example from looking at rough faults

- Supershear transients are more likely on rough, i.e. non planar faults
- Supershear is observed even at low background shear stress (outside the classical Burridge-Andrews range)


[Bruhat, et al. 2016]



So what is the sticking point here?




So what is the sticking point here?



So what is the sticking point here?

“The rupture is sub-Rayleigh”




“The rupture is supershear”

So what is the sticking point here?


“The rupture is sub-Rayleigh”

Transition is somewhere here

“The rupture is supershear”




So what is the sticking point here?



- Observational studies focus on the well-developed part of the supershear rupture, a vague location of the transition is deduced a posteriori
- Numerical studies focus on generating that transition without knowing what are the actual field conditions are for the transition
- **Need for a physics-based method to locate the transition sub-Rayleigh/supershear**

What is the stress intensity at the crack tip?

Solutions to describe the state of stress around a crack tip using Linear Elastic Fracture Mechanics (LEFM) [Williams, 1957, Freund, 1979].




$$\sigma_{\alpha\beta}(r, \theta) = \frac{K_{II}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta)$$

Semi-infinite plain-strain crack in a 2D
homogeneous isotropic linear medium

What is the stress intensity at the crack tip?

Solutions to describe the state of stress around a crack tip using Linear Elastic Fracture Mechanics (LEFM) [Williams, 1957, Freund, 1979].




Stress at a
point around
the crack tip

$$\sigma_{\alpha\beta}(r, \theta) = \frac{K_{II}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta)$$

Semi-infinite plain-strain crack in a 2D
homogeneous isotropic linear medium

What is the stress intensity at the crack tip?

Solutions to describe the state of stress around a crack tip using Linear Elastic Fracture Mechanics (LEFM) [Williams, 1957, Freund, 1979].



Semi-infinite plain-strain crack in a 2D homogeneous isotropic linear medium


Stress at a point around the crack tip

Universal angular functions

$$\sigma_{\alpha\beta}(r, \theta) = \frac{K_{II}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta)$$

What is the stress intensity at the crack tip?

Solutions to describe the state of stress around a crack tip using Linear Elastic Fracture Mechanics (LEFM) [Williams, 1957, Freund, 1979].



Semi-infinite plain-strain crack in a 2D homogeneous isotropic linear medium

Stress at a point around the crack tip


Static stress intensity factor

Universal angular functions

$$\sigma_{\alpha\beta}(r, \theta) = \frac{K_{II}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta)$$

What is the stress intensity at the crack tip?

Solutions to describe the state of stress around a crack tip using Linear Elastic Fracture Mechanics (LEFM) [Williams, 1957, Freund, 1979].



Semi-infinite plain-strain crack in a 2D homogeneous isotropic linear medium

Stress at a point around the crack tip Static stress intensity factor Universal angular functions


$$\sigma_{\alpha\beta}(r, \theta) = \frac{K_{II}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta)$$

For reference $K_{II} = \Delta\tau\sqrt{\pi L}$

where $\Delta\tau$ the stress drop and L the crack length

Now, let the rupture move at a speed v

Due to the moving coordinate system, all the fields undergo a Lorentz-like contraction, affecting both the stress intensity factor K and the angular function f




Static Dynamic stress
intensity factor

$$\sigma_{\alpha\beta}(r, \theta, v) = \frac{K_{II}^{dyn}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta, v)$$

Now, let the rupture move at a speed v

Due to the moving coordinate system, all the fields undergo a Lorentz-like contraction, affecting both the stress intensity factor K and the angular function f



Static Dynamic stress
intensity factor


$$\sigma_{\alpha\beta}(r, \theta, v) = \frac{K_{II}^{dyn}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta, v)$$

For a rupture propagating at speed $v < c_R$

$$K_{II}^{dyn} \approx \frac{1 - v/c_R}{\sqrt{1 - v/c_P}} K_{II}$$

Now, let the rupture move at a speed v

Due to the moving coordinate system, all the fields undergo a Lorentz-like contraction, affecting both the stress intensity factor K and the angular function f



Static Dynamic stress
intensity factor

$$\sigma_{\alpha\beta}(r, \theta, v) = \frac{K_{II}^{dyn}}{\sqrt{2\pi r}} f_{\alpha\beta}^{II}(r, \theta, v)$$

For a rupture propagating at speed $v < c_R$

$$K_{II}^{dyn} \approx \frac{1 - v/c_R}{\sqrt{1 - v/c_P}} K_{II}$$

$$\begin{aligned} \text{As } v &\rightarrow c_R, \\ K_{II}^{dyn} &\rightarrow 0 \\ \sigma_{\alpha\beta} &\rightarrow 0 \end{aligned}$$

The stress concentration will shrink with increasing speed !

Stress intensity at the crack tip controls the extent of off-fault damage

Classical Drucker-Prager failure criteria to compute the extent of the yield region (region where damage is allowed)

$$r_{DP}(\theta, \nu, f) = (K_{II}^{dyn})^2 A(\theta, \nu, f, F)$$

Stress intensity at the crack tip controls the extent of off-fault damage

Classical Drucker-Prager failure criteria to compute the extent of the yield region (region where damage is allowed)

$$r_{DP}(\theta, \nu, f) = (K_{II}^{dyn})^2 A(\theta, \nu, f, F)$$

$$\text{Extent of the damaged region} = \frac{\left(1 - \frac{\nu}{c_R}\right)^2}{\left(1 - \frac{\nu}{c_P}\right)} L(t) \Delta\tau^2 \pi A(\theta, \nu, f, F)$$

Stress intensity at the crack tip controls the extent of off-fault damage

Classical Drucker-Prager failure criteria to compute the extent of the yield region (region where damage is allowed)

$$r_{DP}(\theta, \nu, f) = (K_{II}^{dyn})^2 A(\theta, \nu, f, F)$$

Extent of the
damaged region = $\frac{\left(1 - \frac{\nu}{c_R}\right)^2}{\left(1 - \frac{\nu}{c_P}\right)} L(t) \Delta\tau^2 \pi A(\theta, \nu, f, F)$

Decreases with increasing speed ν

Stress intensity at the crack tip controls the extent of off-fault damage

Classical Drucker-Prager failure criteria to compute the extent of the yield region (region where damage is allowed)

$$r_{DP}(\theta, \nu, f) = (K_{II}^{dyn})^2 A(\theta, \nu, f, F)$$

$$\text{Extent of the damaged region} = \frac{\left(1 - \frac{\nu}{c_R}\right)^2}{\left(1 - \frac{\nu}{c_P}\right)} L(t) \Delta\tau^2 \pi A(\theta, \nu, f, F)$$

Increases with the crack length L


Decreases with increasing speed ν

Stress intensity at the crack tip controls the extent of off-fault damage

Extent of the
damaged region

- Decreases with increasing speed v

**Domain of potential damage
(Drucker-Prager failure criterion)
for a crack propagating with
uniform rupture velocity**




[Jara, Bruhat, et al., submitted]

Stress intensity at the crack tip controls the extent of off-fault damage

Extent of the damaged region

- Decreases with increasing speed v
- Increases with crack length L



What could it mean for supershear transition?

Theoretical method valid when the rupture is sub-Rayleigh $v < c_R$

But, to transition to supershear, the rupture has to first bypass c_R !


We expect to see shrinkage of the near-fault damage zone at the transition sub-Rayleigh/supershear

→ Verification using two numerical codes for dynamic rupture and damage generation

FDEM numerical methods [Okubo, et al., JGR, 2019]


- Combined Finite-Discrete Element Method (FDEM) to produce dynamically activated off-fault fracture networks [Rougier, et al. 2016]
- During sub-Rayleigh, extent of the off-fault fracture zone grows linearly with the rupture propagation.
- Spatial extent of the off-fault damage zone drops dramatically when transitioning to supershear regime

[Okubo, et al., JGR, 2019]



FDEM numerical methods [Okubo, et al., JGR, 2019]


Closeness to failure and coseismic off-fault fracture pattern of a supershear transition using FDEM numerical methods



[Jara, Bruhat, et al., submitted, using the method developed in Okubo, et al., JGR, 2019]

Micromechanics approach [Thomas & Bhat, GJI, 2018]

Closeness to failure and damage pattern of a supershear transition using a homogenized law for microcracks



[Jara, Bruhat, et al., submitted, using the method developed in Thomas & Bhat, GJI, 2018]

What we've learned from fracture mechanics and numerical modeling

- Stress intensity at the crack tip evolves with the rupture velocity
- As the rupture velocity approaches the Rayleigh wave speed, before transitioning to supershear, the stress intensity reduces
- As a result, the region affected by the stress intensity decreases in size as well, leading to a sudden shrinkage of the near-fault damage zone

What we've learned from fracture mechanics and numerical modeling

- Stress intensity at the crack tip evolves with the rupture velocity
- As the rupture velocity approaches the Rayleigh wave speed, before transitioning to supershear, the stress intensity reduces
- As a result, the region affected by the stress intensity decreases in size as well, leading to a sudden shrinkage of the near-fault damage zone

IS THIS REAL?